

COE-CON-COX-NORMAL

COE-NORMAL This is a test of some basic reports
 Start with a COE report and send this again and again until the result is ACK
 COE-CON-NORMAL Next is the CON report, send a COE and a CON until both have got ACK
 COE-CON-COX-NORMAL Next is a COX report, send a COE, a CON and a second CON and a COX until all have got ACK
 FM-COE-CON-COX-NORMAL Next is a test of FM=M manually generated reports
 Change the colour of the line to green as soon as the version of the report is accepted
 Fill in the **Accepted date**

All mandatory elements that are not listed will be filled in with correct values
 *In some cases all values will be tested and in others only some.

Be sure you get an ACK on your report before sending a correction or cancellation.

This scenario is only to verify that a COE report can be received correctly and cancelled by the master and by the FMC

COE-NORMAL		Test of COE and FM=C		Expected RET		Accepted date
MA	RC	TM	Content of the report	RS	RE	
COE-NORMAL		COE		ACK	0	
		COE	with cancellation of COE	ACK	522	
		COE		ACK	0	
		COE	with cancellation of COE FM=C	ACK	522	

This scenario is only to verify that a CON report can be received correctly and cancelled by the master or by the FMC

COE-CON-NORMAL		Test of CON and FM = C		Expected RET		Accepted date
MA	RC	TM	Content of the report	RS	RE	
COE-CON-NORMAL		COE		ACK	0	
		CON	in ; only for NOR vessels	ACK	0	
		CON	cancellation of CON in	ACK	522	
		CON	in ; only for NOR vessels	ACK	0	
		CON	cancellation of CON in FM=C	ACK	522	
		COE	cancellation of COE	ACK	522	

This scenario is only to verify that a COX report can be received correctly and cancelled by the master or by the FMC

COE-CON-COX-NORMAL		Test of COX and FM =C		Expected RET		Accepted date
MA	RC	TM	Content of the report	RS	RE	
COE-CON-COX-NORMAL		COE		ACK	0	
		CON	in ; only for NOR vessels	ACK	0	
		CON	out	ACK	0	
		COX		ACK	0	
		COX	cancellation of COX	ACK	522	
		COX		ACK	0	
		COX	cancellation of COX FM=C	ACK	522	
		COX		ACK	0	

This scenario is only to verify that COE,CON and COX reports can be received when having FM marking M

FM-COE-CON-COX-NORMAL		Test of FM=M		Expected RET		Accepted date
MA	RC	TM	Content of the report	RS	RE	
FM-COE-CON-COX-NORMAL-M		COE	FM=M	ACK	0	
		CON	in ; only for NOR vessels, with FM=M	ACK	0	
		CON	out with FMC =M	ACK	0	
		COX	with FM = M	ACK	0	
		COX	cancellation of COX with FM =M	ACK	522	
		COX	with FM = M	ACK	0	

This scenario is only to verify that old COE,CON and COX reports can be received when having FM marking D

FM-COE-CON-COX-NORMAL		Test of FM=D, The reports have to be old data		Expected RET		Accepted date
MA	RC	TM	Content of the report	RS	RE	
FM-COE-CON-COX-NORMAL-D		COE	FM=D	ACK	0	
		CON	in ; only for NOR vessels, with FM=D	ACK	0	
		CON	out with FMC =D	ACK	0	
		COX	with FM = D	ACK	0	
		COX	cancellation of COX with FM =D	ACK	522	
		COX	with FM = D	ACK	0	